

```

                                Z_PAYROLL_2_PDF_TOP.txt
*-----*
*   Include                      Z_PAYROLL_2_PDF_TOP                      *
*-----*
*   Top Include for REPORT Z_PAYROLL_2_PDF and Z_PAYLETTER_2_PDF          *
*-----*
*
*                               D E C L A R A T I O N S
*
*-----*
*   S t r u c t u r e   T y p e s                                         *
*-----*
TYPES: BEGIN OF ty_pernr,
        pernr TYPE persno,
        END OF ty_pernr.

*-----*
*   T a b l e   T y p e s                                                 *
*-----*
TYPES: tt_pernr                      TYPE STANDARD TABLE OF ty_pernr.

*-----*
*   T a b l e   S t r u c t u r e s                                       *
*-----*
TYPES: ts_pernr                      TYPE ty_pernr.

*-----*
*   ( G l o b a l )   I n t e r n a l   T a b l e s                       *
*-----*
DATA:  gt_selstab                TYPE rsparams_tt,
        gt_pernr                TYPE tt_pernr,
        gtl_pdf                 TYPE ty_tline, " Binary store for PDF
        gt_pdf                  TYPE STANDARD TABLE OF solix,
        SOLI_TAB                type SOLI_TAB.
DATA  e_binary_length           TYPE i.
data  e_xstring                 TYPE xstring.
DATA  lt_solix                  TYPE solix_tab.
DATA  my0001                    TYPE pa0001.

DATA:  ls_pernr                  TYPE ty_pernr,
        lv_spool                 TYPE rspoid.

*-----*
*   G l o b a l   S t r u c t u r e s                                     *
*-----*
DATA:  gs_params                 TYPE pri_params,
        gsi_params               TYPE pri_params.
DATA:  ta_tlinetab              TYPE tline_tab,
        ls_tlinetab             TYPE tline,
        lf_spras                TYPE spras,
        lf_country              TYPE land1,
        lf_pernr                TYPE pernr_d,
        lt_p0002                TYPE STANDARD TABLE OF pa0002,
        ls_p0002                TYPE pa0002,
        lf_sprsl                TYPE pad_spras,
        lf_rufnm                TYPE pad_rufnm,
        lf_vorna                TYPE pad_vorna,
        lf_BSNR                TYPE pa0002-perid,
        lf_yearperiod           TYPE char20.

*-----*
*   G l o b a l   F i e l d s                                           *
*-----*
DATA:  gf_pernr                 TYPE p_pernr,
        gf_abkrs                TYPE abkrs,

```

```

                                Z_PAYROLL_2_PDF_TOP.txt
gf_molga                        TYPE molga,
gf_valid                        TYPE c,
gf_path                         TYPE localfile,
gf_path_u                      TYPE localfile,
gf_messtext                    TYPE char200,
gf_pdf_bytecount               TYPE i.
DATA: w_document                TYPE REF TO cl_document_bcs,
      m_monthnr                 like T247-MNR,
      m_langu                   like sy-langu,
      m_month                    like T247-LTX,
      w_mail_subj                TYPE string.

*-----*
*  C o n s t a n t s                                     *
*-----*
CONSTANTS: co_true              TYPE boole_d    VALUE 'X',
           co_false             TYPE boole_d    VALUE ' ',
           co_device             TYPE rspopname  VALUE 'LOCL',
           co_ext                TYPE char4      VALUE '.pdf',

*-- Constants used in the body of the Email (HTML)
c_htm                TYPE char3    VALUE 'HTM',
c_style_start         TYPE char255  VALUE '<FONT face=Arial size=2>',
c_new_line            TYPE char255  VALUE '<br>',
c_link_start          TYPE char128  VALUE '<A href="www.ciber.nl">',
c_link_text           TYPE char32   VALUE 'Click here',
c_link_end            TYPE char4    VALUE '</A>',
c_space(6)            TYPE c        VALUE '&nbsp;',

*-- Used as an Example for displaying space between texts in Email body
c_emp1(6)             TYPE c        VALUE 101001,
c_emp2(6)             TYPE c        VALUE 101002,
c_emp3(6)             TYPE c        VALUE 101003.

DATA: lf_filename type RLGRAP-FILENAME,
      my_len type i.
DATA cf_error      TYPE boole_d.

```